

Determination of Planck's constant using LEDs

The purpose of this lab activity is to determine Planck's constant by measuring the turn-on voltage of several LEDs




1. Introduction

Light-emitting diodes (LEDs) convert electrical energy into light energy. They emit radiation (photons) of visible wavelengths when they are “forward biased” (i.e. when the voltage between the p side and the n-side is above the “turn-on” voltage). This is caused by electrons from the “n” region in the LED giving up light as they fall into holes in the “p” region.

The graph below shows the current -voltage curve for a typical LED. The 'turn-on' voltage V_t times e (electron charge) is about the same as the energy lost by an electron as it falls from the n to the p region, and this is also approximately equal to the energy of the emitted photon.



If we measure the minimum voltage V_t required to cause current to flow and photons to be emitted, and we know (or measure) the wavelength of the emitted photons and use it to calculate the photon energy hf , we always find that $eV_t < hf$. Some of the photon energy is supplied by thermal energy.



2. Procedure:

Light-emitting diodes require a series load resistor to prevent thermal runaway - unlimited forward current - from destroying them. Our experiment is conceptually as shown above, with some modification: we use AC voltage rather than DC, so the voltage keeps varying periodically, and the LED lights up whenever the voltage is large enough to overcome the depletion barrier. Then also a current flows across the junction (through the diode). We measure the applied voltage with an oscilloscope which allows visualization of time dependent electric signals. We measure the current by measuring the voltage across the 100Ω resistor. By measuring the voltage V_t at which the LED "turns on", i.e. at which current flows (current >0), we can determine the energy of the photons (it is $\approx eV_t$). This voltage is different for the LEDs of different color. We know the wavelength of the light emitted by the different LEDs (and therefore the frequency). By using the equation $eV_t \approx hf$, we can determine Planck's constant h . This is only approximate, since, as mentioned above, $eV_t < hf$, because some of the energy can be supplied by thermal motion. A better method is therefore to plot V_t vs frequency and determine the slope of a straight trendline fitting the data. The slope equals h measured in eV, and the intercept gives an estimate of the contribution from thermal energy.

3. Analysis

- Make a table with a row for every LED, containing λ (given), f ($=c/\lambda$, $c=3\cdot 10^8$ m/s, V_t (measured), h (calculated using h (in eV) $= V_t/f$)
- Determine mean value of h and standard deviation
- Graph V_t (on y-axis = ordinate) vs frequency (on x-axis = abscissa) and determine the slope of the straight line – this is h in units of eV ("electron Volts")
- The value of h obtained from the slope of the straight line may be different from that obtained in part b (from averaging the values of h obtained from different LEDs) – any explanation? What is the meaning of the intercept? Which of the two determinations is more reliable?
-

4. References

- <http://hyperphysics.phy-astr.gsu.edu/hbase/electronic/led.html#c2>
- <http://micro.magnet.fsu.edu/primer/java/leds/basicoperation/>
- <http://www.youtube.com/watch?v=oVtbWFphcCk>
- <http://www.youtube.com/watch?v=J10QmuB9WCY>

5. Information about the LEDs

LED #	color	wavelength (nm)	max current (mA)
1	blue	480±40	20
2	green	560±15	20
3	yellow	590±15	20
4	red	635±15	20
5	dark red	665±15	20
6	infrared	950±20	20

6. Appendix:

a. More detail about LEDs: A light-emitting diode is a p-n junction rectifier. p-type material contains excess “holes” (missing electrons – positive) and n-type material contains excess electrons. When p- and n-type semiconductors are brought together to form a p-n junction, electrons with energies in the conduction band diffuse from the n-side to the p-side and holes with energies in the valence band diffuse from the p-side to the n-side. Without an externally applied voltage, a diffusion potential V_D is generated in the depletion layer between the n-type and the p-type material. The diffusion potential prevents more electrons and holes from leaving the n- and p- regions, respectively, and entering the opposite regions. When an external forward biased voltage V is applied, the potential barrier is reduced. When $V \sim V_D$ the height of the barrier is approximately zero and electrons can flow from the n-side to the p-side, and a current will flow across the junction from the p-type to the n-type material. As the current flows electrons are continually meeting holes in the p-n interface. When an electron drops in to a hole level a photon is released with energy $E=hf$. The frequency or wavelength of light (color) will depend on the semiconductor material and diffusion voltage V_D . The diode will turn on when $V= V_D$. During the recombination energy is released. It can be released in the form of a photon with energy $hf \sim E_g$, where E_g is the width of the band gap of the semiconductor, which in turn is $\approx eV_D \approx eV_t$. The LED junction must be thin and/or transparent so the emitted light can escape.

b. Use of Excel for this experiment

You should use a spreadsheet program (e.g. Excel) to do the data analysis.

Excel hints:

- i. Getting average and standard deviation: In Excel you can get the average using the function AVERAGE(data range), and standard deviation by using function STDEV(data range)
- ii. Scatter plot: it is useful to have two columns adjacent to each other, first column f , then column V_t . Select the data in these two columns and then do “insert scatter” – this will generate a scatter plot of V_t (y-axis) vs f (x-axis). Then right-click on data points in chart and select “add trendline”. In the pop-up menu, select “linear”, “display equation on chart” and “display R-value on chart”
- iii. Parameters of trendline: If you want to use the slope from the linear trendline in calculations (e.g. get h from slope), select an appropriate cell in your

spreadsheet and type =slope(y-value range, x-value range). This will put the slope of the line into the cell. You can also get h directly, typing =slope(y-value range, x-value range) Similarly you could also get the intercept by typing “= intercept(y-value range, x-value range)”

Explanation about average, standard deviation, uncertainties:

(1) if you repeat measurements of the same quantity several times, in general you will see that the results vary from one attempt to the other; this is due to measurement errors. Repetition of measurements can be used to get a more precise estimate of the “true value” and also give information about the measurement precision.

(2) if you have N measurements X_i ($i=1,2,\dots,N$) of some quantity X, the average value is

given by
$$\bar{X} = \frac{1}{N} \sum_{i=1}^N X_i$$

(this means: sum all the values X_i , i.e. take $X_1 + X_2 + \dots + X_N$, and then divide by the total number of measurements, N).

(3) the “standard deviation” is a quantity which provides an estimate for the precision with which you determined your best estimate of X. The square of the standard deviation (also called the “sample variance”) is given by

$$\sigma_x^2 = \frac{1}{N-1} \sum_{i=1}^N (X_i - \bar{X})^2 ,$$

i.e. to calculate it, you take the sum of the squares of the deviations between the individual measurements X_i and the average, and then divide by (N-1). The standard deviation (sometimes also called the “root-mean-squared deviation”) is then given by

the square root of this:
$$\sigma_x = \sqrt{\frac{1}{N-1} \sum_{i=1}^N (X_i - \bar{X})^2} .$$

In Excel, you can get the standard deviation by using the function STDEV(data range).

(4) You can also try to estimate your measurement precision by making an educated guess (“guesstimate”) of how precisely you know the voltage and the frequency . Let $\delta V = \sigma_v$ be the uncertainty (“error”, “imprecision”) of your measurement of the turn-on voltage V_t , and $\delta f = \sigma_f$ the uncertainty of the frequency, then the “relative uncertainty”

$$\frac{\delta h}{h} = \frac{\sigma_h}{h} \text{ of } h \text{ determined from this is: } \frac{\delta_h}{h} = \frac{\sigma_h}{h} = \frac{\sigma_v}{V} = \sqrt{\left(\frac{\sigma_v}{V}\right)^2 + \left(\frac{\sigma_f}{f}\right)^2}$$